

## Instructions for Running the ESC\_Test Harness

### Overview

The initial run of the ESC Test Harness will convert the included waveforms from binary (.dat) to .tdms format prior to playing the waveforms. As a result, there will be a 60 second delay before the waveforms plays. Once each of the waveforms are converted to .tdms, each waveform will play sequentially with no delay. The new TDMS files will appear in the “Test” directory as in Fig. 8.

### Required equipment

- PXI
- Ni VST 5646

### Required Software

- Windows 7 or higher
- LabVIEW 2017

Download the ESC\_Test\_Harness-master

Copy the up-zipped file to a computer hosting LabVIEW and PXI.

### Starting the ESC Tester Start Python Server, start LabVIEW Web server and run web browser (Fire fox)

- 1) Locate and double click the “StartUp.bat” file located in the “ESC\_Test\_Harness-master” folder as in Fig. 1.
  - The Python status window will appear as in Fig. 1a.
  - The ESC\_Server will appear as in Fig. 2a.
- 2) Start the ESC\_Server by right clicking on the “v1” as in Fig. 2a. Select “Start” to initiate the session (Fig. 2b). You will see Debug Web service windows appears as in Fig. 3. Click “OK”.
  - The ESC Test Harness interface will appear as in Fig. 4. Press “log in”.
  - The default user name and password are “admin” and “default”.
- 3) To stop the Python web server, select the running Python screen. Select “Ctrl + C”  
To Stop the LabVIEW player right click on “v1” as in Fig. 2c. Select “Stop”




Figure 1: Start up in directory




Figure 1a: Python window




Figure 2a: LabVIEW project window




Figure 2b: Start up LabVIEW player




Figure 2c: Stop LabVIEW player




Figure 3: LabVIEW Debug window




Figure 4: ESC user interface




Figure 5: waveform file




Figure 6: Location for global variables status

- 4) Locate the “waveforms.txt” file located in your “Test” folder. See Fig. 5. Enter the full path of the “waveform.txt” file into the “Input File Location” and press “Input\_From\_File” to play the waveforms as in Fig. 4.

The status of the waveform conversions and waveform playing can be monitored on the GlobalVariables.vi Front Panel.

- 4) Go to the LabVIEW project and expand the folder “99 – Others”. Double click the “GlobalVariables.vi”. The GlobalVariables.vi front panel will appear as in Fig. 7.




Figure 7: Status of waveform playback

**Note: the waveforms can be viewed on your spectrum analyzer. See optional step 6 for configuring your spectrum analyzer.**




Figure 8: TDMS files




Figure 9: Location of SCPI commands

### This is an optional Step

#### 5) Configuring your spectrum analyzer

The spectrum analyzer settings are controlled with Standard Commands for Programmable Instruments (SCPI) commands. The address for the VISA connection will need to be changed.

- To change the VISA address, go to the LabVIEW Project Explorer, expand the Dependencies tab.
- Locate and open the "SpectrumAnn SCPI commands.vi" as in Fig. 9.
- Enter the VISA address for your instrument. See Fig. 11.
- Expand the menu in the case structure to reveal the spectrum analyzer settings for the different waveforms as in Fig. 12.

If you prefer manual configurations, the "local" key on the spectrum analyzer will end the remote session.




Figure 10: Spectrum analyzer configuration front panel




Figure 11: Spectrum analyzer settings




Figure 12: Spectrum analyzer settings